

# Installing the Monitoring Station



For Uptime Infrastructure Monitor 7.8.5 and later, the `vcruntime140.dll` must be installed prior to installing or upgrading. If the `.dll` is not available during the upgrade or installation process, you may receive a message that the procedure failed.

To fix this issue:

1. Exit the installer by clicking **OK**.
2. Install the Microsoft Visual C++ 2015 Redistributable, available at the following URL: <https://www.microsoft.com/en-us/download/details.aspx?id=48145>
3. Re-run Uptime installer `Uptime-7.8.5-windows.exe`.  
If you currently have Visual C++ 2017 Redistributable installed on top of VC++ 2015 Redistributable, then the required registry key may not exist in your environment. To resolve this issue, you must "repair" VC++2017. For more information, see <https://developercommunity.visualstudio.com/content/problem/262841/vc-runtime-redistributable-update-deletes-registry.html>.

## Upgrade

Proceed to the appropriate section depending on your Monitoring Station platform:

- [Installing on Windows](#)
- [Installing on Linux](#)
- [Post-Installation Tasks](#)

## Installing on Windows



**Windows Installations Only:** When running the Uptime Infrastructure Monitor installation on Windows, an initial splash screen appears and then disappears. There is an approximately 5-minute waiting period until the main installer loads. This is due to the installer unpack. You can see two Uptime processes running in task manager. This is normal behavior.

On Windows, the Uptime Infrastructure Monitor Monitoring Station is installed using a graphical installer that guides you through the steps of the installation process.

1. Ensure you are logged in to the Monitoring Station system as the local administrator.  
Uptime Infrastructure Monitor may not function properly if the Monitoring Station is installed when you are logged in as a domain or non-local administrator.
2. Double-click the executable installer:  
`uptime-<version#>-windows.exe`
3. On the introduction screen, click **Next**.
4. On the **License Agreement** screen, carefully read all of the Uptime Infrastructure Monitor end-user license agreement, then click the **accept** checkbox, and click **Next**.
5. Select the installation size that most closely matches your monitored deployment.  
Your selection determines how Uptime Infrastructure Monitor's underlying configuration is configured (for example, the MySQL buffer pool size and open connections cap). These parameters can be changed to match a different selection after installation.
6. Accept or modify the default install location for the Monitoring Station files (`C:\Program Files\uptime software\uptime`), then click **Next**.  
This is the location of the core Uptime Infrastructure Monitor components (i.e., the Data Collector and Web server), as well as the Controller; the DataStore location is set in the next step.
7. Accept or modify the default install location for the DataStore (`C:\Program Files\uptime software\uptime\datastore`), then click **Next**.  
Because the DataStore can grow very large (in excess of 100 GB), you can install the DataStore on another file system if you are monitoring a large number of systems and retaining data for extended periods.
8. On the **Configuration Options** page, in the **Web Server Settings** section, optionally configure the Uptime Infrastructure Monitor Web server:
  - **Web Server Name**  
The hostname of the system through which users will access the Web server's user interface. This name is written to the `<installDirectory>\apache\conf\httpd.conf` file, which contains configuration information for the Web server used by Uptime Infrastructure Monitor.
  - **Web Server Port**  
The port through which the Web server for the Monitoring Station will listen for requests. The port number is written to the `httpd.conf` file.
9. Configure the Uptime Infrastructure Monitor **Controller Settings**:
  - **Controller Port**  
This is the port through which the Uptime Infrastructure Monitor Controller actively listens for API calls. This port number is written to the `<installDirectory>\controller\etc\jetty-ssl.xml` file.
  - **SSL Distinguished Name**
  - **SSL Passphrase**  
Provide keystore information so that the install process can generate the issuer for the Controller's self-signed certificate. This information includes a distinguished name and passphrase. By default, the distinguished name is the Controller hostname, which is a mandatory attribute; make this as complete as needed (e.g., `CN=hostname,O=Organization,OU=ITServices,ST=California,C=US`). The passphrase must be at least six characters long.
10. In the DataStore Settings section, optionally configure the Database Port through which the DataStore will listen for requests.  
The port number is written to the `uptime.conf` file
11. Select the Start menu location and user access option, then click **Next**.

12. Click **Next** to begin the installation.  
The installation process will take several minutes.
13. When the software is installed, click **Finish**.  
The following occurs:
  - the Web server and DataStore services are started
  - the DataStore is populated with default data
  - the Data Collector is started
  - the Controller service is left in a stopped state
  - the Monitoring Station user interface is launched in your default browser
14. Proceed to the [Post-Installation Tasks](#) section.

## Installing on Linux

On Linux, the Uptime Infrastructure Monitor Monitoring Station installer is a console application.

1. Ensure you have logged in to the Monitoring Station system as `root`.
2. Type the following command:  
`sh uptime-<version>-linux.bin`  
It can take up to several minutes for the components of the installer to be extracted from the `.bin` file.
3. On the Introduction page, press **Enter** to continue.
4. On the License Agreement page, carefully read all of the Uptime Infrastructure Monitor end-user license agreement. Press **Enter** to scroll through the agreement.
5. At the DO YOU ACCEPT THE TERMS OF THIS LICENSE AGREEMENT? (Y/N) prompt, type `y` and press **Enter**.
6. Choose Install Folder: Accept the default install directory for the Monitoring Station files (`/usr/local/uptime`) or enter a new, absolute path, then press **Enter**.  
This is the location of the core Uptime Infrastructure Monitor components (i.e., the Data Collector and Web server), as well as the Controller; the DataStore location is set in the next step.



The uptime user account must be able to access the specified directory.

7. Choose DataStore Path: Accept the default install directory for the DataStore (`/usr/local/uptime/datastore`) or enter a new, absolute path, then press **Enter**.  
Because the DataStore can grow very large (in excess of 100 GB), you can install the DataStore on another file system if you are monitoring a large number of systems and retaining data for extended periods.
8. Choose Configuration Size: Select the installation size that most closely matches your monitored deployment.  
Your selection determines how Uptime Infrastructure Monitor's underlying configuration is configured (for example, the MySQL buffer pool size and open connections cap). These parameters can be changed to match a different selection after installation.
9. DataStore Port: Accept the default DataStore port (3308) or enter a new one, then press **Enter**.  
This is the port through which the DataStore will listen for requests. The port number is written to the `uptime.conf` file.
10. Web Server Name: Accept the default hostname for Uptime Infrastructure Monitor's Web server component or enter a new one, then press **Enter**.  
This is the name of the system through which users will access the Uptime Infrastructure Monitor Web interface. This name is written to the `<installDirectory>/apache/conf/httpd.conf` file, which contains configuration information for the Web server used by Uptime Infrastructure Monitor.
11. Web Server Port: Accept the default Web server port (9999) or enter a new one, then press **Enter**.  
This is the port through which the Web server will listen for requests. The port number is written to the `httpd.conf` file.
12. Uptime Controller Port: Accept the default Uptime Controller port (9997) or enter a new one, then press **Enter**.  
This is the port through which the Uptime Infrastructure Monitor Controller listens for API calls. The port number is written to the `<installDirectory>/controller/etc/jetty-ssl.xml` file.
13. Keystore Configuration: Provide keystore information so that the install process can generate the issuer for the Controller's self-signed certificate.
  - a. Distinguished Name: Accept the default distinguished name (the hostname of the installation system) or enter a new one, then press **Enter**.  
Only the common name (CN) attribute is required, but you can make the name as complete as needed (e.g., `CN=hostname, O=Organization, OU=ITServices, ST=California, C=US`).
  - b. Keystore Password: Enter and confirm a password.  
This password must be at least 6 characters long.
14. Pre-Installation Summary: Review the configured options, then press **Enter**.  
The installation process will take several minutes.
15. When the installation is complete, press **Enter**.  
The following occurs:
  - the Web server and DataStore are started
  - the DataStore is populated with default data
  - the Data Collector is started
  - the Controller service is left in a stopped state
16. Press **Enter** again to exit the installer.
17. Proceed to the [Post-Installation Tasks](#) section.

## Post-Installation Tasks

After installing the Uptime Infrastructure Monitor Monitoring Station, you will need to do the following:

- set up the administrator account and SMTP server when you first log in

- install the license for Uptime Infrastructure Monitor
- add systems
- add users

## Set Up the Administrator Account and SMTP Server

Once the Monitoring Station is installed, connect to it using the hostname and port defined during the installation process: `http://<hostname>:<port>`

The first user to log into Uptime Infrastructure Monitor should be the system administrator. The administrator account has the default user name `admin`, and at first login, you will have to set the password and email address for this administrator account. To set up the administrator account, do the following:

1. Access the Monitoring Station in a supported Web browser:  
`http://<hostname>:<port>`  
Where `<hostname>` is the name or IP address of the system that is running the Uptime Infrastructure Monitor Monitoring Station. For example:  
<http://localhost:9999>
2. At the Uptime Infrastructure Monitor login screen, enter the password for the administrator in the **Password** field.
3. Re-enter the password in the **Confirm Password** field.
4. Enter an appropriate address in the **Administrator's Email** field.
5. Enter your SMTP hostname in the **SMTP Server** field.  
Uptime Infrastructure Monitor needs this information configured immediately in order to send alerts. You can modify this information after installation (see [SMTP Server](#) for more information).
6. Click the **Login** button.  
You have set up Uptime Infrastructure Monitor's main administrator account.

## Install a License to Use Uptime Infrastructure Monitor

See [License Information](#) for more information.

## Add Systems

The fastest way to begin monitoring your infrastructure is to use [Auto Discovery](#) to efficiently assemble a monitored inventory.

Afterward, you can fine-tune your monitored inventory. See [Managing Your Infrastructure](#) for more information.

## Add Users

You will need to create user roles (e.g., for administration, alert investigation, and report access) and assign individual users or user groups to them. See [User Management](#) for more information.

## Secure the Uptime Infrastructure Monitor Virtual Appliance

If you have installed Uptime Infrastructure Monitor as a virtual appliance, the default user ID and password used to access the virtual OS is `root` and `uptime`, respectively. This level of access is required for system-level Uptime Infrastructure Monitor tasks such as custom scripting, debugging, and working with the database. For security purposes, it is strongly recommended that you change the default root-level password provided for the Uptime Infrastructure Monitor virtual appliance OS.

## Secure the Uptime Controller

If you are planning to use the Uptime Controller, there are further steps to consider. See [Controller Security](#) for more information.