Installing the Monitoring Station

Proceed to the appropriate section depending on your Monitoring Station platform:

- Windows
- Linux
- VMware Virtual Appliance

Installing on Windows

On Windows, the up.time Monitoring Station is installed using a graphical installer that guides you through the steps of the installation process.

- 1. Ensure you are logged in to the Monitoring Station system as the local administrator.
- up.time may not function properly if the Monitoring Station is installed when you are logged in as a domain or non-local administrator. 2. Double-click the executable installer:
- up.time-<version#>-windows.exe
- 3. On the introduction screen, click Next.
- On the License Agreement screen, carefully read all of the up.time end-user license agreement, then click the accept check box, and click Next.
 Accept or modify the default install location for the Monitoring Station files (C:\Program Files\uptime software\uptime), then click Next. This is the location of the core up.time components (i.e., the Data Collector and Web server); the DataStore location is set in the next step.
- Accept or modify the default install location for the Data Store (C:\Program Files\uptime software\uptime\DataStore), then click Next. Because the DataStore can grow very large (in excess of 100 GB), you can install the DataStore on another file system if you are monitoring a large number of systems and retaining data for extended periods.
- Optionally configure the Web server and DataStore components, then click Next:
 - Web Server Name

The hostname of the system through which users will access the Web server's user interface. This name is written to the httpd.conf file, which contains configuration information for the Web server used by up.time.

Web Server Port

The port through which the Web server for the Monitoring Station will listen for requests. The port number is written to the httpd.conf file.

- DataStore Port
- The port through which the DataStore will listen for requests. The port number is written to the uptime.conf file.
- 8. Accept or modify the default location for program shortcuts, then click Next.
- 9. Click Next to begin the installation.
- The installation process will take several minutes.
- 10. When the software is installed, click Finish.
 - The following occurs:
 - the Web server and DataStore are started
 - the DataStore is populated with default data
 - the Data Collector is started
 - the Monitoring Station user interface is launched in your default browser
- 11. Proceed to the Post-Installation Tasks section.

Installing on Linux

æ

On Linux, the up.time Monitoring Station installer is a console application.

- 1. Ensure you have logged in to the Monitoring Station system as root.
- 2. Type the following command:
- sh up.time-<version>-<platform>.bin where <platform> is the operating system on which you are installing up time (i.e., you are installing up tinstalling up time (i.e., you are installing up time (i.e., you are

where <platform> is the operating system on which you are installing up.time (i.e., up.time-<version>-rhes.bin for Red Hat Enterprise Linux, or up.time-<version>-sles.bin for SUSE).

- It can take up to several minutes for the components of the installer to be extracted from the .bin file.
- 3. On the Introduction page, press Enter to continue.
- 4. On the License Agreement page, carefully read all of the up time end-user license agreement. Press Enter to scroll through the agreement.
- 5. At the DO YOU ACCEPT THE TERMS OF THIS LICENSE AGREEMENT? (Y/N) prompt, type y and press Enter.
- 6. Accept the default install directory for the Monitoring Station files (/usr/local/uptime) or enter a new location, then press Enter.

This is the location of the core up time components (i.e., the Data Collector and Web server); the DataStore location is set in the next step.

The uptime user account must be able to access the specified directory.

- Accept the default install directory for the DataStore (/usr/local/uptime/datastore) or enter a new location, then press Enter. Because the DataStore can grow very large (in excess of 100 GB), you can install the DataStore on another file system if you are monitoring a large number of systems and retaining data for extended periods.
- 8. Accept the default hostname for up time's Web server component or enter a new one, then press Enter.
- This is the name of the system through which users will access the Web server's user interface. This name is written to the http.conf file, which contains configuration information for the Web server used by up time.
- 9. Accept the default Web server port (9999) or enter a new one, then press Enter.
- This is the port through which the Web server will listen for requests. The port number is written to the httpd.conf file.
- Accept the default DataStore port (3308) or enter a new one, the press Enter. This is the port through which the DataStore will listen for requests. The port number is written to the uptime.conf file.

- 11. On the Pre-Installation Summary page, review the configured options, then press Enter.
 - The installation process will take several minutes.
- 12. When the installation is complete, press Enter.
 - The following occurs:
 - the Web server and DataStore are started
 - the DataStore is populated with default data
 - the Data Collector is started
- 13. Press Enter again to exit the installer.
- 14. Proceed to the Post-Installation Tasks section.

VMware Virtual Appliance

Refer to Installing the up.time Virtual Appliance for directions on installing up.time within your VMware environment. This guide is packaged with the up. time Virtual Appliance download on the support Portal downloads page.

Post-Installation Tasks

After installing the up.time Monitoring Station, you will need to do the following:

- · set up the administrator account and SMTP server when you first log in
- install the license for up.time
- add systems
- add users

Set Up the Administrator Account and SMTP Server

Once the Monitoring Station has been installed, connect to it using the hostname and port defined during the installation process: http://<hostname>: <port>

The first user to log into up.time should be the system administrator. The administrator account has the default user name admin, and at first login, you will have to set the password and email address for this administrator account. To set up the administrator account, do the following:

- Access the Monitoring Station in a supported Web browser: http://<hostname>:<port> Where <hostname> is the name or IP address of the system that is running the up.time Monitoring Station. For example: http://localhost.9999
 At the up time login acrean enter the persuard for the administrator in the **Depresent** field.
- 2. At the up.time login screen, enter the password for the administrator in the Password field.
- 3. Re-enter the password in the Confirm Password field.
- 4. Enter an appropriate address in the Administrator's Email field.
- 5. Enter your SMTP hostname in the SMTP Server field.
- up time needs this information configured immediately in order to send alerts. You can modify this information after installation SMTP Server 6. Click the Login button.

You have set up up.time's main administrator account.

Install a license to use up.time

See License Information for more information.

Add Systems

The fastest way to begin monitoring your infrastructure is to use Auto Discovery to efficiently assemble a monitored inventory.

Afterward, you can fine-tune your monitored inventory. See Managing Your Infrastructure for more information.

Add Users

You will need to create user roles (e.g., for administration, alert investigation, and report access) and assign individual users or user groups to them. See U ser Management for more information.