## **Configuring the up.time Controller**

## Securing the Controller

If you plan on using the up.time Controller by integrating API functions with the up.time Web interface, consider doing the following to prevent several common browser-related warnings when navigating secure and non-secure pages within the same web page:

- Enable SSL for the up.time Web interface, using the instructions found in Implementing SSL for the Web Interface.
- Purchase a valid SSL certificate for the up.time web interface to avoid warnings about a self-signed certificate in the browser.
   The Controller installs an unsigned and unverified certificate as part of its installation process. For installations in a production environment, a valid key should be purchased and installed on the Controller.

## **Reflecting Configuration Changes in the Proxy**

As part of the up.time installation process, a proxy is configured in the <uptimeDirectory>\apache\conf\httpd.conf file. This provides ease of use with the up.time Controller, as it simplifies many API programming tasks, and helps to ensure the Controller remains secure.

By default the proxy section should look like the following:

```
# proxy settings
LoadModule proxy_module modules/mod_proxy.so
LoadModule proxy_http_module modules/mod_proxy_http.so
ProxyRequests Off
<Proxy *>
 Order deny,allow
 Allow from all
</Proxv>
ProxyPass /uptime http://<uptimeHost>:9996/uptime retry=0
ProxyPassReverse /uptime http://<uptimeHost>:9996/uptime
ProxyPass /gadgets/service http://<uptimeHost>:9996/gadgets/service retry=0
ProxyPassReverse /gadgets/service http://<uptimeHost>:9996/gadgets/service
ProxyPass /gadgets/instances http://<uptimeHost>:9996/gadgets/instances retry=0
ProxyPassReverse /gadgets/instances http://<uptimeHost>:9996/gadgets/instances
# ssl proxy settings
LoadModule ssl_module modules/mod_ssl.so
SSLProxyEngine on
ProxyPass /api https://<controllerHost>:9997/api retry=0
ProxyPassReverse /api https://<controllerHost>:9997/api
```

The proxy is configured to work using the default options and configuration choices made when up time is installed:

- the Monitoring Station (<uptimeHost> above) and up.time Controller (<controllerHost> above) are part of the same installation (i.e., they have the same value), and assumed to be on the same host
- the port the Controller uses to communicate with up time is 9997

If there are changes to the way up time has been deployed on the network, you will need to modify the Apache Web server configuration file, accordingly:

Deployment Change	Affected Proxy Setting
change the API hostname or move the API to another server	<controllerhost></controllerhost>
change the API port	9997
when on running on different servers, the Monitoring Station's network location is changed	<uptimehost></uptimehost>

After making any change, restart the up.time Web Server service (on the correct up.time instance, if applicable) to apply these changes. Then verify you have correctly configured the proxy by browsing to https://<uptimeMonitoringStation>/api. The behavior should be identical to browsing to the up.time Controller at https://<uptimeController>/api.

## **Controller Configuration Parameters**

The following list details several common up.time Controller configuration tasks.

Task	Setting	Configuration Location in	Notes
		<uptimedirectory>\con</uptimedirectory>	
		troller	

change Controller port	up.time Contoller port	\etc\jetty-ssl.xml	To change the port, find this line within jetty-ssl.xml: <set name="Port"><property default="9997" name="jetty.port"></property></set> Update the 9997 value to an unassigned port, then restart the up.time Controller service.
change Controller DataStore target	database connection settings	\resources\uptime- controller.conf	Example connection fields and options are provided for all supported DataStore back-end platforms. By default, the up.time Controller uses a standard MySQL DataStore connection (unless you updated these values during installation). dbType=MYSQL dbHostname=localhost dbPort=3308 dbName=uptime dbUsername=uptime dbJdbcProperties= To change the connection details, update these fields with your database platform information. There are example entries in the configuration file.
indicate where PHP sessions are stored	PHP session directory	\resources\uptime- controller.conf	By default, the phpSessionDirectory parameter is not defined, and up.time will look for stored sessions in the Apache work space: <ul> <li><uptimedirectory>\apache\tmp (Windows)</uptimedirectory></li> <li>/usr/local/uptime/apache/tmp (Linux)</li> </ul>
change Controller logging level	logging level	\resources\uptime- controller.conf	The Controller automatically logs events in the /logs directory. Logging levels include the following:  • TRACE • DEBUG • INFO • INFO • WARN • ERROR • FATAL By default, the logging level is INFO. After you have updated your settings, restart the up.time Controller service.
install new Controller SSL certificate	SSL communicat ion	\etc\jetty-ssl.xml	To install a new key, follow steps 3 and 4 from the jetty How to Configure SSL Page, then restart the up. time Controller service.