

up.time Deployment Templates

During [up.time's installation](#), one of three deployment templates was selected, depending on the size of your monitored environment. The choice determined how certain resources were allocated, and subsequent hardware requirements:

Deployment Template	Elements	Minimum RAM	Minimum CPU Type
Small	<100	2 GB	2-core CPU
Medium	250–1000	16 GB	6-core CPU
Large	1000+	32 GB	12-core CPU

Each deployment template ensures the underlying configurations (for example, for the bundled MySQL database and JRE) match the likely resource demands to generate reports, dashboards, and perform queries. The following summarizes these configurations:

Configuration Parameter	Small	Medium	Large
MySQL buffer pool size	120 MB	2 GB	4 GB
MySQL log file size	20 MB	512 MB	1 GB
MySQL maximum open connections	151	201	301
Java heap size	1 GB	2 GB	4 GB
service threads	50	100	200
Data Collector maximum open connections	100	150	250
up.time Controller heap size	512 MB	1 GB	2 GB

Modifying the Deployment Template

After initial installation, if you need to accommodate a larger number of monitored Elements, you can manually change the deployment templates using one of two methods:

The first, more direct, option is to individually modify parameters that make up a template. This allows you to deviate somewhat from the prescribed configuration values for a template:

Configuration Parameter	Configuration File and Location (relative to the up.time directory)	Parameter Name	Default Deployment Values (S, M, L)	
MySQL buffer pool size	/mysql/my.ini	innodb_buffer_pool_size=	120M	2G 4G
MySQL log file size	/mysql/my.ini	innodb_log_file_size=	20M	512M 1G
MySQL maximum open connections	/mysql/my.ini	max_connections=	151	201 301
Java heap size	Linux: /uptime.jncf Windows: \UptimeDataCollector.ini	Linux: -Xmx<size> Windows: vm.heapsize.preferred=	Linux: -Xmx1G -Xmx2G -Xmx4G	Windows: 1024m 2048m 4096m
service threads	/uptime.conf	serviceThreads=	50	100 200
Data Collector maximum open connections	/uptime.conf	connectionPoolMaximum=	100	150 250
up.time Controller heap size	Linux: /controller/service/start.sh Windows: \controller\service\UptimeController.ini	Linux: -Xmx<size> Windows: vmarg.2=	-Xmx512m -Xmx1024m -Xmx2048m	

The recommended option to change a deployment template is to use the sample configuration files that are found in the <uptimeInstall>/sample directory as a starting point. This option moves you to a different deployment template in the least amount of steps.

Modifying Sample Templates

Update the DataStore configuration:

1. Stop the DataStore service (uptime_datastore on Linux, or "up.time Data Store" on Windows)
2. Move the `ib_logfile0` and `ib_logfile1` files, found in the `<uptimeInstall>/datastore/data/` directory, to a backup location.
3. Back up the MySQL `my.ini` configuration file, which is found in the `<uptimeInstall>/mysql/` directory.
4. Copy the `<uptimeInstall>/sample/<size>/<os>/my.ini` template file to the `<uptimeInstall>/mysql/` directory, replacing the existing one.
5. Edit the `my.ini` file, replacing all `$VARIABLE$` instances with values that match your up.time deployment (for example, `$DATASTORE_PORT$` and `$USER_INSTALL_DIR$`)
6. Start the DataStore service
You can confirm the change was successful by referring to the `<uptimeInstall>/datastore/data/<hostname>.err` log. Look for output similar to the following:

```
140110 14:26:28 InnoDB: Initializing buffer pool, size = 2.0G
140110 14:26:29 InnoDB: Completed initialization of buffer pool
140110 14:26:29 InnoDB: Log file .\ib_logfile0 did not exist: new to be created
InnoDB: Setting log file .\ib_logfile0 size to 512 MB
InnoDB: Database physically writes the file full: wait...
InnoDB: Progress in MB: 100 200 300 400 500
140110 14:26:33 InnoDB: Log file .\ib_logfile1 did not exist: new to be created
InnoDB: Setting log file .\ib_logfile1 size to 512 MB
InnoDB: Database physically writes the file full: wait...
InnoDB: Progress in MB: 100 200 300 400 500
```

Update the up.time Data Collector configuration:

1. Back up the `uptime.conf` file, which is found in the `<uptimeInstall>/` directory.
2. Back up the Data Collector configuration file (`uptime.jcnf` on Linux, or `UptimeDataCollector.ini` on Windows), which is found in the `<uptimeInstall>/` directory.
3. Copy the `uptime.conf`, and `uptime.jcnf` or `UptimeDataCollector.ini` files from the `<uptimeInstall>/sample/<size>/<os>/` directories to the `<uptimeInstall>/` directory, replacing the existing ones.
4. Edit both files, replacing all `$VARIABLE$` instances with values that match your up.time deployment (for example, the `MS_STRING_FS` classpath variable, and `$DATASTORE_HOST$`).
5. Restart the up.time data-collection service (`uptime_core` on Linux, or "up.time Data Collector" on Windows)

Update the up.time Controller configuration:

1. Back up the up.time Controller configuration file:
 - Linux: the `start.sh` script, which is found in the `<uptimeInstall>/controller/service/` directory
 - Windows: the `UptimeController.ini` configuration file, which is found in the `<uptimeInstall>\controller\service` directory
2. Copy the `start.sh` or `UptimeController.ini` file from the `<uptimeInstall>/sample/<size>/<os>/` directory to the `<uptimeInstall>/controller/service/` directory, replacing the existing one.
3. Edit the file, replacing all `$VARIABLE$` instances with values that match your up.time deployment.
4. Restart the up.time Controller service (`uptime_controller` on Linux, or up.time Controller on Windows)

Update the up.time Web server:

1. Back up the `php.ini` up.time Web server configuration file, which is found in the `<uptimeInstall>/apache/conf/` directory.
2. Copy the `php.ini` file from the `<uptimeInstall>/sample/<size>/<os>/` directory to the `<uptimeInstall>/apache/conf/` directory, replacing the existing one.
3. Edit the file, replacing all `$VARIABLE$` instances with values that match your up.time deployment (for example, `$USER_INSTALL_DIR$`).
4. Restart the up.time Web server (`uptime_httpd` on Linux, or "up.time Web Server" on Windows).