Auto Discovery for VMware vCenter Inventories

A VMware vCenter server acts as a central control point for a VMware vSphere datacenter. It includes ESX hosts, VMs, as well as groupings such as clusters, datacenters, vApps, and resource pools. A VMware vCenter server's inventory, system configurations, storage profiles, and performance data can be represented in Uptime Infrastructure Monitor alongside physical systems and network devices. When a VMware vCenter is added, all of its resources are detected and can be automatically imported.

Using Auto Discovery

To use Auto Discovery to add a VMware vCenter server, do the following:

- In the Infrastructure panel, click Auto Discovery. The Auto Discovery window appears.
- 2. Select Discover VMware Inventory using vCenter, then click Next.
- 3. Enter a descriptive **Display name in Uptime** for the VMware vCenter server.
- 4. Optionally enter a **Description** of the system.
- 5. In the **Host Name** field, provide the server's hostname or IP address.
- 6. Accept or modify the default Web Services Port through which Uptime Infrastructure Monitor connects to the server.
- 7. In the **Username** and **Password** fields, provide the login information for the VMware vCenter administrator.
- 8. Select the Group into which you want to add discovered devices.
- 9. Configure Notification Settings.

When a vSync operation is performed to check for changes to the VMware vCenter inventory, these check boxes indicate whether Uptime Infrastructure Monitor sends notifications about, or performs scripted actions in response to, newly discovered ESX servers or VMs. (For more information, see Managing vSync.)

10. Configure Additional VM Guest Performance Data Collection settings.

These options enable additional monitoring for VMware vCenter VMs using the Uptime Infrastructure Monitor agent or WMI. (See Standalone Monitoring for vCenter VMs for more information.)

- For the Uptime Infrastructure Monitor agent, indicate the port on which it is listening, and whether it is securely communicating with Uptime Infrastructure Monitor using SSL.
- For data collection via WMI, indicate the host and domain on which WMI is implemented, and the username and password required for access.

In both cases, you can also use a global configuration if they are configured. See Configuring Global Data Collection Methods for more information.



The WMI-related options only exist if the Monitoring Station is running on a Windows system.

11. Click Save.

The VMware vCenter inventory is added to Uptime Infrastructure Monitor in its own Infrastructure group.