API Overview

All API commands can be accessed using this general format:

https://<hostname>:<port>/api/<api_version>/<end_point>/<id>/<task>

- hostname: the URI for the up.time Controller installation
- port: the up.time Controller listener port, typically 9997
- api_version: the version of the API to run commands against (see Version Control below)
- end_point: the type of object you want to work with in up.time (see Endpoints below)
- id: the numerical ID of the object you are interested in
- task: where supported, specific tasks to be executed against the provided object

Methods

Accessing the standard format URL using different HTTP methods produces different results on the target object:

- POST: add an object or trigger an action
- PUT: edit an object
- DELETE: delete an object
- GET: view the details of an object

Returned Results

All returned results are provided in JSON format. Successfully completed requests will return an HTTP code in the 200 range.

Authentication

Authentication to the API is based on the basic HTTP basic authentication template: each request to the API must provide a username and password pair. To safeguard this information, all requests to the up.time API must use SSL communication.

Each user in up.time has access to the API. User-visibility and role-based permissions are applied to each API call, ensuring users are only able to access and modify the same information they would be able to access from the up.time UI.

Version Control

The version of the API you wish to access is embedded directly into the URL. Bug fixes and non-breaking feature changes will be made without changing the version number. Major feature changes or breaking changes will introduce a new version number. Backwards support for previous API version is currently not defined.

Non-breaking changes include:

- adding fields or functions to input requests
- adding fields to returned data

Breaking changes include:

- · changing or removing fields or functions on input requests
- · changing or removing fields in returned data
- changing the URI of any existing function

Endpoints

Endpoints define the different types of up time objects that you can work with using the API. The currently supported endpoints include the following:

```
/elements - up.time Elements
/monitors - up.time service monitors
/groups - up.time Element groups
```

The following is a summary of presently available resources:

Working with Elements

list all Elements and attached service monitors; display an Element's information and attached service monitors; display an Element's information and its current status:

GET GET

GET

Working with service monitors

list all service monitors; display a specific server monitor; display status information for a service monitor:

```
GET
GET
GET
/api/v1/monitors
/api/v1/monitors/{id}
/api/v1/monitors/{id}/status
```

Working with Element groups

list all Element groups, member Elements, and monitors; list an Element group's member Elements and monitors; display the status of an Element group's member Elements and monitors:

```
GET
GET
GET
/api/v1/groups
/api/v1/groups/{id}
/api/v1/groups/{id}/status
```

Error Handling

If the provided command produces an error, an HTTP status in the 400 range will be returned including a specific status code and a message with further details about the error. All error messages are returned in JSON format and look like the following:

```
{
  "error": "Required field missing",
  "errorDescription": null
}
```